

Phildar.

FÉDÉRICA Coat

Yarn P. INUIT col. DARK
Pattern details sizes 34/36 to 50/52

Sheet T23 539



Beginner Level



Photo is non-contractual

« EXCLUSIVE MODELS » all commercial reproduction is prohibited without special authorisation from **PHILDAR**
PP YARNS & Co Editeur RCS 808 534 895 ©PHILDAR 2022

FEDÉRICA COAT

T23 - 539



Beginner Level



Estimated time between 20 and 30 hours to finish

To knit this project, you'll need:

Size 34/36: 8 skeins of PHIL INUIT in the colourway DARK
Size 38/40: 8 skeins of PHIL INUIT in the colourway DARK
Size 42/44: 9 skeins of PHIL INUIT in the colourway DARK
Size 46/48: 9 skeins of PHIL INUIT in the colourway DARK
Size 50/52: 10 skeins of PHIL INUIT in the colourway DARK

Yarn composition: 100 % Polyester

Tools and materials needed:

PPY knitting needles n° 8 (8 mm) or other size following your gauge swatch
Stitch markers
1 tapestry needle

Gauge swatch & obtaining the right dimensions for your project:

When knitting your gauge swatch, it's always best to do so "in pattern". For this model we'll be using stockinette and your 8 mm needles. 9 sts. (stitches) and 11 rws (rows) = a square of 10 cm x 10 cm.

CONSTRUCTION

The different size options have been colour-coded in order to help you follow the instructions for the size you wish to knit with more ease.

KNITTING THE BACK PIECE

Step 1: With your 8 mm needles, CO (cast on) 48 - 50 - 54 - 58 - 64 sts.

Step 2: Knit in stockinette, meaning: RS (right side): K all sts. WS (wrong side): P all sts. Keep repeating these 2 rws. Knit in stockinette until you've reached a tot. height of 47 cm.

Step 3: PM (place stitch marker) on the selvedge sts. (the first and last stitch of the rw), indicating the armholes.

Step 4: Cont. (continue) knitting in stockinette until you've reached a tot. height of 69 - 70 - 71 - 72 - 73 cm.

Step 5: Shape the shoulders in the following way:

BO (bind off) 6 sts. and finish the rw. Rep. in the following rw. BO 7 sts. and finish the rw. Rep. in the following rw.

BO (bind off) 7 sts. and finish the rw. Rep. in the following 3 rws.

BO (bind off) 7 sts. and finish the rw. Rep. in the following rw. BO 8 sts. and finish the rw. Rep. in the following rw.

BO (bind off) 8 sts. and finish the rw. Rep. in the following 3 rws.

BO (bind off) 9 sts. and finish the rw. Rep. in the following 3 rws.

Step 7: We have 22 - 22 - 24 - 26 - 28 sts. on our needle, BO all sts.

Step 8: PM after the 7th - 7th - 8th - 9th - 10th st. from each side (right and left), indicating the end of the shoulder seams.

KNITTING THE RIGHT HALF FRONT PIECE

Step 1: With your 8 mm needles, CO 20 - 21 - 23 - 25 - 28 sts.

Step 2: Knit in stockinette, meaning: RS (right side): K all sts. WS (wrong side): P all sts. Keep repeating these 2 rws. Knit in stockinette until you've reached a tot. height of 47 cm.

Step 3: PM on the last selvedge st. (the last stitch of the rw), indicating the armholes.

Step 4: Cont. knitting in stockinette until you've reached a tot. height of 69 - 70 - 71 - 72 - 73 cm.

Step 5: Shape the shoulder in the following way:

Knit 1 rw (on the RS). BO 6 sts. and finish the rw. Knit 1 rw. BO 7 sts. and finish the rw. Knit 1 rw and BO the last 7 sts.

Knit 1 rw (on the RS). BO 7 sts. and finish the rw. Rep. these 2 rws 1 time. Knit 1 rw and BO the last 7 sts.

Knit 1 rw (on the RS). BO 7 sts. and finish the rw. Knit 1 rw. BO 8 sts. and finish the rw. Knit 1 rw and BO the last 8 sts.

Knit 1 rw (on the RS). BO 8 sts. and finish the rw. Rep. these 2 rws 1 time. Knit 1 rw. BO the last 9 sts.

Knit 1 rw (on the RS). BO 9 sts. and finish the rw. Rep. these 2 rws 1 time. Knit 1 rw and BO the last 10 sts.

KNITTING THE LEFT HALF FRONT PIECE

Knit steps 1 to 2.

Step 3: PM on the first selvedge st. (the first stitch of the rw), indicating the armhole.

Step 4: Cont. knitting in stockinette until you've reached a tot. height of 69 - 70 - 71 - 72 - 73 cm.

Step 5: Shape the shoulder in the following way:

BO 6 sts. and finish the rw. Purl 1 rw. BO 7 sts. and finish the rw. Purl 1 rw. BO the last 7 sts.

BO 7 sts. and finish the rw. Purl 1 rw. Rep. these 2 rws 1 time. BO the last 7 sts.

BO 7 sts. and finish the rw. Purl 1 rw. BO 8 sts. and finish the rw. Purl 1 rw. BO the last 8 sts.

BO 8 sts. and finish the rw. Purl 1 rw. Rep. these 2 rws 1 time. BO the last 9 sts.

BO 9 sts. and finish the rw. Purl 1 rw. Rep. these 2 rws 1 time. BO the last 10 sts.

KNITTING THE SLEEVES

Step 1: With your 8 mm needles, CO 30 - 32 - 34 - 36 - 38 sts.

Step 2: Knit in stockinette, meaning: RS (right side): K all sts. WS (wrong side): P all sts. Keep repeating these 2 rws. Knit in stockinette while making inc. (increases) in the following way:

Inc. 1 st. at the beginning and end of rws: 9, 17, 25, 33 and 43.

Inc. 1 st. at the beginning and end of rws: 9, 17, 25, 33 and 43.

Inc. 1 st. at the beginning and end of rws: 11, 19, 27, 35 and 43.

Inc. 1 st. at the beginning and end of rws: 11, 19, 27, 35 and 43.

Inc. 1 st. at the beginning and end of rws: 9, 17, 25, 33 and 41.

We now have: 40 - 42 - 44 - 46 - 48 sts.

Keep knitting until you've reached a tot. height of 47 - 47 - 46 - 46 - 43 cm. BO all sts.

Find the middle of the top of the sleeve and PM, indicating point M (see the pattern illustration).

Knit the second sleeve in the same way.

KNITTING THE POCKETS

Step 1: With your 8 mm needles, CO 16 sts.

Step 2: Knit in stockinette until you've reached a tot. height of 17,5 cm.

Step 3: BO all sts.

Step 4: Knit a second pocket in the same way.

SEAMING & FINISHING TOUCHES

Step 1: Place the back and front (both halves) pieces right sides together and seam the shoulders until the stitch markers, using the backstitch and following the green lines in the pattern illustration.


Step 2: Place one sleeve between the 2 stitch markers of the back and front pieces. Place the sleeve and body right sides together. Match up the M point of the sleeve with the M point of the shoulder seam.

Assemble the sleeve using backstitch, following the red lines in the pattern illustration.

Assemble the other sleeve in the same way.

Step 3: Seam the sides of the back and front pieces (right sides together), using the mattress stitch and following the blue lines in the pattern illustration.

Step 4: Sew the pockets onto the body, by placing them along the side seams at 6 - 7 - 8 - 9 - 10 cm from the bottom.



All measurements in cm

○ = stitch marker

M = middle of the sleeve and shoulder seam